


# FiveM/RedM

## (GTA:V/Red Dead: 2)


- [Updating your server](#)
- [Getting a license key](#)
- [Server Settings](#)
- [Installing addons](#)

# Updating your server


1. Click on GTA:V/Red Dead: 2 in the sidebar



2. Click on Versions



3. Make sure the latest version is selected in the dropdown (If the latest version of the software is not listed do let us know)



4. Click on the install button next to the dropdown to install the selected version.
5. Once you get a notification saying its finished installing you can start your server up again.

# Getting a license key

FiveM and RedM servers require you to get a license key from the FiveM website, the guide below will show you how you can generate a license key to use on your server.

## Step 1

Go to <https://keymaster.fivem.net/> then click on the sign in link to login or create an account

## Step 2

To create a new license key click on New in the navigation bar

## Step 3

Enter the details requested, you can find the IP address of your server by going to the Access page of the panel

## Step 4

Click on the generate button

## Step 5

In the details section of the page that loads click on copy then paste the text into the License Key field in the settings of your server.

# Server Settings

On this page you will find an explanation of each setting on the settings page along with some recommendations.

Setting	Default value	Description
TCP IP/Port	0.0.0.0:30120	The IP and port the game and any addon uses to communicate between the server and the player <b>We recommend keeping this as the default value</b>
UDP IP/Port	0.0.0.0:30120	The IP and port the game and any addon uses to communicate between the server and the player <b>We recommend keeping this as the default value</b>
Hostname	FXServer, but unconfigured	The name given to your server in the server list
Max Clients	32	The maximum number of players that can connect
RCON Password	Empty	Password used when connecting via RCON
Endpoint Privacy	Enabled	This enables/disables the external log output, we recommend enabling this for privacy reasons
Scripthook Allowed	Disabled	Enabling this option will allow you to use addons that depend on scripthook, however, it may also allow players to connect with other modifications.
License Key	changeme	This is your license key for the server, to get a license key follow the guide linked below

# Installing addons

Addons form a key aspect of a GTA:V FiveM server as it allows you to customise the experience that players have on your server.

To install addons on your server go to FiveM/RedM on the panel then click on Files

Now on the files page double click on the following folder server-data > resources

You can now upload your addon by dragging and dropping the addon on the file list.